
Deploying tags on penguins

(Barbara Wienecke, Australian Antarctic Division, barbara.wienecke@aad.gov.au)

Determining position of tag

- put penguin into a weighing bag with head sticking out
- put penguin into prone position
- roll up the lower end of bag to expose lower back
- make sure the back is straight by gently holding onto legs and extending them straight backwards
- lift tail straight into air and measure four fingers wide away from base of tail (distance = red line)
- attach tag no lower than that; you need to keep the preen gland free and accessible



- cover base of tag with Loctite 401 (make sure that glue is at room temperature; otherwise is won't cure)
- remeasure position if necessary
- put tag into position on lower back and press down firmly for 10 seconds

Note:

Loctite 401 is a contact glue; avoid getting it onto your fingers!



Penguin inside weighing bag. The bottom of the bag is rolled up to get access to the lower back.


- take cable tie and feed $^{\sim}$ 0.5 cm away from the side of tag underneath the feathers and up the other side of tag
- make sure that the tick end of the cable tie sits on the side of the tag close to the penguins back before tightening it
- repeat (two cable ties are sufficient)





The glue is quite strong once it sets properly. The cable ties give extra hold.


• one cable ties are closed and put into position (thick end where tie feeds through onto the side of the tag) use a cable tie gun (or a pair of pliers) to tighten them so that there are no loops





- when using a cable tie gun, press the tag firmly down while tightening and cutting the tie
- make sure that no sharp ends are left sticking out

• Finally, put more glue around the outside of the tag, especially the front





Any questions, please contact me. Cheers, Barbara